


Manage Available Server Connections


Servers are managed in the **Apriso Servers** box, which is displayed upon clicking the  button on the main login box.

System administrators can prepopulate the list of available servers using the ServersSettings.xml file available under <drive>\Program Files\Dassault Systemes\DELMIA Apriso 2025\WebSite\Downloads\PB2 on the DELMIA Apriso server. All the necessary instructions are included in the file.



To Add a Server to the Available List

1. Click the **Add...** button to invoke the Apriso Servers box for entering the required server information.



The dialog box is titled "Apriso Servers" and has a subtitle "For entering the required server information." It contains the following fields:

- Server alias:
- Name (address):
- ☐ Use SSL
- Authentication:

At the bottom are "OK" and "Cancel" buttons.

2. Enter an alias for the server and a correct address string.


When using 3DPassport authentication, a full domain name for the server is required.

If the server supports SSL encryption, select the **Use SSL** check box.

3. Click **OK** to finish adding the server, which will now appear on the list of available servers.

To Change the Properties of a Server on the Available List

1. Select the server you would like to change the properties for, and click the **Change...** button to launch the box for changing the required server information.



The dialog box is titled "Apriso Servers" and has a subtitle "For changing the required server information." It contains the following fields:

- Server alias:
- Name (address):
- ☐ Use SSL
- Authentication:

At the bottom are "OK" and "Cancel" buttons.

2. Make the desired changes and click **OK** to confirm.

To Remove a Server from the Available List

Select the server you would like to remove and click the **Remove** button. A dialog box will appear to confirm the deletion of the server.