


Step 1: Link a Layout to a Screen

Create screens based on a layout as described in [Getting Started](#). The layout will be then linked automatically. Use the following steps if a screen is not linked to a layout (the screen was created using a different method) or to link a new layout to an existing screen.


To Link a Layout to a Screen

1. Use one of these methods:


- Click  (Link) on the **Screen: General Tab**



- Right-click the screen in **Entity Explorer** and select the **Link Layout** option




- ▶ Click  **Layout** on the screen workspace (this option is available if a screen is not currently linked to a layout)




2. Choose the layout to link from the **Layouts** pop-up window.

You can choose a predefined one from templates.



After the layout is linked it is not added as a new entity itself in Entity Explorer because only panels are added under the screen. However, the name of the linked layout is added to the name of the screen:



For more information on layouts, see [Layout Overview](#).