


Step 3: Define Actions


To define an Action, choose one of the options described below.

Add a New Action to an Existing Panel

In this option, you can add a new Action to an existing Panel on a Screen with a linked View using the right-click menu:



The Action is added under that particular Panel:




Use an Action Inherited from a Linked View

Methods


The different methods for using this option to define an Action are described below.

Use an Original Action from the View




In this case, you cannot change any properties of this Action (the Properties pane options are greyed-out).

Override the Original Action




After overriding the Action you can then change its properties, which then become the properties of this Action on the Screen.

Additionally, after overriding the Action, the icon changes:



Disable the Action

To disable the Action, first you need to override it.



After disabling the Action, its icon is greyed-out. It thus cannot be used, but you can change its properties.

Action Icons

In the options above, notice the differences between icons used to describe different types of Actions:

Icon	Action
	Actions newly added to a Panel.
	Action linked automatically with a Panel (as its part).

Action Properties

All the Action properties are described in the [View Action Properties](#) section.